



Disclaimer:

As a condition to the use of this document and the information contained herein, the SWGIT requests notification by e-mail before or contemporaneously to the introduction of this document, or any administrative, legislative, or adjudicatory hearing or other proceeding (including discovery proceedings) in the United States or any foreign country. Such notification shall include: 1) the formal name of the proceeding, including docket number or similar identifier; 2) the name and location of the body conducting the hearing or proceeding; 3) the name, mailing address (if available) and contact information of the party offering or moving the document into evidence. Subsequent to the use of this document in a formal proceeding, it is requested that SWGIT be notified as to its use and the outcome of the proceeding. Notifications should be sent to: SWGIT@yahoogroups.com

Redistribution Policy:

SWGIT grants permission for redistribution and use of all publicly posted documents created by SWGIT, provided that the following conditions are met:

1. Redistributions of documents, or parts of documents, must retain the SWGIT cover page containing the disclaimer.
2. Neither the name of SWGIT, nor the names of its contributors, may be used to endorse or promote products derived from its documents.

Any reference or quote from a SWGIT document must include the version number (or create date) of the document and mention if the document is in a draft status.



Section 9

General Guidelines for Photographing Tire Impressions

Introduction

The purpose of this document is to describe the proper method of photographing tire impression evidence by qualified personnel.

Recommended Equipment Includes:

- Professional camera, minimum 35mm or digital SLR with a minimum eight (8) megapixel native resolution, with interchangeable lenses, manual override for exposure and focus
- Detachable flash with a six (6) foot extension cord or a flash with remote capabilities to allow for sided lighting
- Remote shutter release
- Sturdy tripod mount capable of various angles and positions
- Artificial light sources (e.g., flood lights, flashlights)
- Level/Angle finder
- Suitable B&W and color negative film or digital storage media
- Flat rigid scales
- Tape measure
- Photographic log
- Reflector
- Device for blocking ambient light

Procedure for Tire Impression Photography¹

A typical standard operating procedure should include the following:

- 1) Locate visible impressions to be photographed.
- 2) Prepare photographic log or worksheet as per agency policy
- 3) Select suitable film or digital media.
- 4) Once the overall, midrange and close-up views of the area have been documented without scales and markers, photograph the overall and midrange views of the area with identifying markers and scales using appropriate lighting.
- 5) To document details of the impression for examination, photograph close-up views of the impression with identifiers and scales using appropriate lighting. Each image must fill the frame with the impression and scales:
 - a) Mount camera on tripod with the focal plane parallel to the impression.
 - b) Manually focus on the bottom of the impression and close aperture to maximize depth of field (e.g. set aperture to f16 or f22).
 - c) If using digital camera, set camera to the highest resolution and uncompressed or with lossless compression. (e.g. RAW or TIFF).
 - d) Take multiple overlapping exposures, mapping the entire tire impression, In this manner:
 - Light each overlapping section of the impression to bring out maximum detail. For a long tire impression, a series of overlapping photographs of 12 inches each should be taken. A tape measure should be extended along side the entire length of the impression for orientation purposes.
 - e) Multiple exposures using various settings/bracketing and lighting techniques may be required. A minimum of three images should be taken with oblique lighting at least 100 degree increments around the entire tire impression.
 - f) If impression is processed (e.g. with fingerprint powder or chemicals), re-photograph after each process.

¹ Reference SWGTREAD Guide for the Forensic Documentation and Photography of Footwear and Tire Impressions at the Crime Scene

REFERENCE LIST

SWGIT and SWGIT/SWGDE documents can be found at:

www.swgit.org

<i>Section</i>	<i>Title</i>
Section 1	Overview of SWGIT and the Use of Imaging Technology in the Criminal Justice System
Section 2	Considerations for Managers Migrating to Digital Imaging Technology
Section 3	Guidelines for Field Applications of Imaging Technologies in the Criminal Justice System
Section 4	Recommendations and Guidelines for Using Closed-Circuit Television Security Systems in Commercial Institutions
Section 5	Guidelines for Image Processing
Section 6	Guidelines and Recommendations for Training in Imaging Technologies in the Criminal Justice System
Section 7	Best Practices for Forensic Video Analysis
Section 8	General Guidelines for Capturing Latent Impressions Using a Digital Camera
Section 9	General Guidelines for Photographing Tire Impressions
Section 10	General Guidelines for Photographing Footwear Impressions
Section 11	Best Practices for Documenting Image Enhancement
Section 12	Best Practices for Forensic Image Analysis
Section 13	Best Practices for Maintaining the Integrity of Digital Images and Digital Video
Section 14	Best Practices for Image Authentication
Section 15	Best Practices for Archiving Digital and Multimedia Evidence (DME) in the Criminal Justice System
Section 16	Best Practices for Forensic Photographic Comparison
Section 17	Digital Imaging Technology Issues for the Courts
SWGIT/SWGDE	Proficiency Test Program Guidelines
SWGIT/SWGDE	Guidelines and Recommendations for Training in Digital and Multimedia Evidence
SWGIT/SWGDE	Recommended Guidelines for Developing Standard Operating Procedures
SWGIT/SWGDE	Glossary of Terms